МЕДІЛТЕК

MT7986 QA Tool User Guide


ICB/RSD/SA3 Kasper

Notes

- * : Annotation
- 1 : Essential steps
- 1 : Function (optional)
- blue: noteworthy items




Flow



1. Setup

- DUT Default IP: 192.168.1.1
- To connect to DUT, network IP should be set to same IP domain (ex: 192.168.1.2 or 192.168.1.3,...etc.)







2. Make Sure DUT is Connected to Testing PC/notebook

- Open command window.
- Key-in "ping 192.168.1.1 -t" to ping DUT continuously.


```
■ 系統管理員: 命令提示字元 - ping 192.168.1.1 -t
                                                                       - -
C:\Users\mtk16972>ping 192.168.1.1
Ping 192.168.1.1 (使用 32
      192.168.1.1:
                          =32 time<1ms TTL=64
                           32 time<1ms TTL=64
                          =32 time<1ms TTL=64
                           =32 time<1ms TTL=64
                          =32 time<1ms TTL=64
                          =32 time<1ms TTL=64
                          =32 time<1ms TTL=64
                          =32 time<1ms TTL=64
                          =32 time<1ms TTL=64
                          =32 time<1ms TTL=64
                           =32 time<1ms TTL=64
                           32 time<1ms TTL=64
      192.168.1.1: 位元
                         =32 time<1ms TTL=64
```





2. Make Sure DUT is Connected to Testing PC/notebook

- If "ping 192.168.1.1 -t" fail
 - 1. Go to device manager
 - Find "Network Adapters"
 - choose the one connecting to DUT
 - → right click, choose "properties"
 - 3. Disable Energy-Efficient Ethernet





3. Entering Test Mode


1. By SSH (by Ethernet cable)

- Key-in "ssh root@192.168.1.1".
- key-in "ated" right after "root@LEDE:~#" to enter test-mode.

2.By Console

- Select port, and baud rate set to 115200.
- Key-in "ated" right after "root@LEDE:/#" to enter test-mode.





Could NOT access by SSH

- If Could NOT access by SSH
 - Key-in "ssh-keygen -R 192.168.1.1" to remove RSA key.

Then Key-in "ssh root@192.168.1.1".



3. Open QA Tool

Open "QATool_Dbg.exe".


*If you can't lunch QA tool (popup can't find wpcap.dll message), please install WinPcap.



Choose "APSOC".



Select corresponded n Select Adapter




Cancel





Press OK


4. Start Using QA Tool




Page	Usage
TX/RX Band 0	G Band TX/RX
TX/RX Band 1	A Band TX/RX
EEPROM	Read/Write/Save EEPROM
RU Page	HE-MU/HE-TB Setting Details

Note: For DBDC: TX/RX page separates into G band →TX/RX, and A band →TX/RX Band1

UI Introduction – Main Page



UI Introduction – Main Page




Contents

#	Category	Items
1		TX a/b/g/n/ac/ax-SU
<u>2</u>	TX	TX HE-MU
<u>3</u>		TX HE-TB
4		RX a/b/g/n/ac/ax-SU
<u>5</u>	RX	RX HE-MU
<u>6</u>		RX HE-TB
<u> 7</u>		EEPROM
<u>10</u>	Debug Tools	DC Tone generate
<u>12</u>		Duplicate Mode (For EMI test)









HE MCS index Combination

V: mandatory support

V: optional support

V: MTK proprietary support

X: un-support

Parameter	RU26	RU52	RU106	RU242 (BW20)	RU484 (BW40)	RU996 (BW80)	RU996x2 (BW80+80)
MU-MIMO	Χ	Χ	V	V	V	V	V
ВСС	V	V	V	V	Χ	Χ	Χ
LDPC	V	V	V	V	V	V	V
1024QAM	V	V	V	V	V	V	V
256QAM	V	V	V	V	V	V	V


AX Support TABLE																
RU26	1ss M0~7	1ss M8~9	1ss M10	1cc M11	2cc M0~7	2ss M8~9			3ss M0~7	3ss M8~9	3ss M10	3ss M11	4ss M0~7	4ss M8~9	4ss M10	4ss M11
BCC	V V	V V	V V	\/	V V	V V	233 10110	V V	V V	V V	V V	V V	V V	V V	433 WITO	433 WITT
LDPC	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V
RU52	1ss M0~7	1ss M8~9	1ss M10	1ss M11	2ss M0~7	2ss M8~9	2ss M10	2ss M11	3ss M0~7	3ss M8~9	3ss M10	3ss M11	4ss M0~7	4ss M8~9	4ss M10	4ss M11
ВСС	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V
LDPC	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V
RU106	1ss M0~7	1ss M8~9	1ss M10	1ss M11	2ss M0~7	2ss M8~9	2ss M10	2ss M11	3ss M0~7	3ss M8~9	3ss M10	3ss M11	4ss M0~7	4ss M8~9	4ss M10	4ss M11
BCC	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V
LDPC	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V
RU242	1ss M0~7	1ss M8~9	1ss M10	1ss M11	2ss M0~7	2ss M8~9	2ss M10	2ss M11	3ss M0~7	3ss M8~9	3ss M10	3ss M11	4ss M0~7	4ss M8~9	4ss M10	4ss M11
BCC	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V
LDPC	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V
RU484	1ss M0~7	1ss M8~9	1ss M10	1ss M11	2ss M0~7	2ss M8~9	2ss M10	2ss M11	3ss M0~7	3ss M8~9	3ss M10	3ss M11	4ss M0~7	4ss M8~9	4ss M10	4ss M11
BCC	X	X	Χ	X	X	X	X	X	X	Χ	X	Χ	X	X	Χ	Χ
LDPC	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V
RU996	1ss M0~7	1ss M8~9	1ss M10	1ss M11	2ss M0~7	2ss M8~9	2ss M10	2ss M11	3ss M0~7	3ss M8~9	3ss M10	3ss M11	4ss M0~7	4ss M8~9	4ss M10	4ss M11
BCC	X	X	Χ	X	X	X	X	X	X	X	X	Χ	X	X	Χ	X
LDPC	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V	V
RU996*2	1ss M0~7	1ss M8~9	1ss M10	1ss M11	2ss M0~7	2ss M8~9	2ss M10	2ss M11	3ss M0~7	3ss M8~9	3ss M10	3ss M11	4ss M0~7	4ss M8~9	4ss M10	4ss M11
BCC	X	X	Χ	X	X	X	Χ	X	X	Χ	X	Χ	Χ	X	Χ	Χ
LDPC	V	V	V	V	V	V	V	V	Χ	Χ	X	Χ	X	Х	Χ	Χ

*1.BCC only support RU size ≤242






TX HE-MU Reference Table



TX- HE MU








Select Band: 0 for G band, 1 for A band*

Note: select Band =0 for G band, and select Band =1 for A band







- Choose RU Category for every BW20
- Those rows are enable only after setting relevant BW in TX/RX page.


 MT7986 000F OA 0.0.273 FEFFFFFFFFFF
- Each row represent BW20 waveform. Select Band: Allocation: RU Index: MCS: 0: Disable 0: Disable · 26 * 3 + 52 * 3 8: Sinale 26 + 106 * 2 Segment 1: LDPC Allocat... Sta ID RU Index Rates Category 12: 106 + 106 13: 242 * 1 14: 484 * 1 MEDIATEK MediaTek Proprietary and Confidential. © 2021 MediaTek Inc. All rights reserved.

6 Allocation (BW20, 26*5+52*2 for example)*






7 Select RU Index (BW20, 26*5+52*2, allcation:1001 for example)*



*Check the RU Index form below (BW20, 26*5+52*2 for example)



20





- Select details:
- 1. MCS rate
- Power Boost Factor(range:-6~+6dB)
 - Resolution: 1/32 dB
 - Example: 1dB → PowerBoost Factor=32
 - -1dB → PowerBoost Factor=-32
- 3. MU NSS: Antenna number
- 4. LDPC: check for LDPC, non-check for BCC
- Stream Idx: select 1
- 6. Length settings: (see next page*)







*Examples

	Ex	ampl	es	User	MU NSS (antenna number)	NSS	Stream Idx	
	106 user1 4ss	+26+2 user2 4ss	106 user3 4ss	User1~4	4	4	1	
		+26+		User1	4	2	1* *Star	nds for 1&2
	user1 2ss	user3	user4	User2	4	2	7 *	1: 1&2 2 starts from 3
	user2	4ss	4ss	User3	4	4	1	
	2ss			User4	4	4	1	
	106	+26+	106	User1	4	1	1	
	user1	user3	user4	User2	4	3	2	
	1ss user2	4ss	4ss	User3	4	4	1	
D	3ss			User4	4	4	1	22

8* MPDU TX Length Setting in HQA

- The table shown below is implemented in QATool already.
 - → choose wanted RUs, directly shows corresponding length.
- Users are able to modify the PSDU length manually.


For NSS=1/2

PSDU Length : Short		_										
RU size	0	1	2	3	4	5	6	7	8	9	10	11
26	32	64	128	128	128	128	128	128	128	128	128	128
52	64	128	256	256	256	256	256	256	256	256	256	256
106	128	256	512	512	512	512	512	512	512	512	512	512
242	256	512	1024	1024	1024	1024	1024	1024	1024	1024	1024	1024
484	512	1024	2048	2048	2048	2048	2048	2048	2048	2048	2048	2048
996	1024	2048	4096	4096	4096	4096	4096	4096	4096	4096	4096	4096
996*2	2048	4096	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192


For NSS=3/4

PSDU Length : long												
RU size	0	1	2	3	4	5	6	7	8	9	10	11
26	128	256	512	512	512	512	512	512	512	512	512	512
52	256	512	1024	1024	1024	1024	1024	1024	1024	1024	1024	1024
106	512	1024	2048	2048	2048	2048	2048	2048	2048	2048	2048	2048
242	1024	2048	4096	4096	4096	4096	4096	4096	4096	4096	4096	4096
484	2048	4096	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192
996	4096	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192
996*2	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192






TX- HE MU(TX/RX Page)



TX HE-TB






RU Page (TX HE-TB)

4 Select Band: 0 for G band, 1 for A band*

Note: select Band =0 for G band, and select Band =1 for A band



- **6** Choose RU Category for every BW20
- Those rows are enable only after setting relevant BW in TX/RX page.



RU Page (TX HE-TB)

Allocation (BW20, 26*3+52*3 for example)




*Check the allocation form below (BW20, 26*3+52*3 for example)


	8 bits indices	#1	#2	#3	#4	#5	#6	#7	#8	#9										
	00000000	26	26	26	26	26	26	26	26	26	00101y2y1y0	26	26	52		26 106				
	00000001	26	26	26	26	26	26	26	5	2	00110y2y1y0	5	2	26	26	26		10)6	
	00000010	26	26	26	26	26	- 5	2	26	26	00111y ₂ y ₁ y ₀	5	2	5	2	26		10	06	
	00000011	26	26	26	26	26	5	2	5	2	01000y ₂ y ₁ y ₀		10)6		26	26	26	26	26
	00000100	26	26	5	2	26	26	26	26	26	01001y ₂ y ₁ y ₀		10			26	26	26		2
	00000101	26	26	5	2	26	26	26	5	2										
	00000110	26	26	5	2	26	5	2	26	26	01010y ₂ y ₁ y ₀		10			26		2	26	26
111	00000111	26	26	5	2	26	5	2	5	2	01011y ₂ y ₁ y ₀		10)6		26	5	2	5	2
	00001000	5	2	26	26	26	26	26	26	26	0110y ₁ y ₀ z ₁ z ₀		10)6		-		10)6	
	00001001	5	2	26	26	26	26	26	5	2	01110000	52 52			2	-	5	2	5	2
	00001010	5		26	26	26	5		26	_	01110001		242-tone RU empty							
1011	00001011	5	2	26	26	26	5	2	5	2	01110010	4			h zero H nding H					е
	00001100	5	2	5	2	26	26	26	26	26	04440044	9			h zero H					e
1101	00001101	5	2	5	2	26	26	26	5	2	01110011			orrespo	nding H	E-SIG-B	Content	Channe	1	
1110	00001110	5	2	5	2	26	5	2	26	26	10y2y1y0Z2Z1Z0		10)6		26		10)6	
1110	00001111	5	2	5	2	26	5	2	5	2	11000y ₂ y ₁ y ₀					242				
EDIATEK	00010y2y1y0	5	2	5	2	-	106	(numb	er of users)		11001y ₂ y ₁ y ₀					484				
	00011y2y1y0	106	(numb	er of u	sers)	-	5	2	5	2	11010y ₂ y ₁ y ₀		996							
	00100y2y1y0	26	26	26	26	26		10	06		11011y ₂ y ₁ y ₀					2*996				

RU Page(TX HE-TB)


- 7 Select RU Index (26*3+52*3, allocation 1011, for example)
- 1011 26 26 26



Select 37/2/3/4/39/40(refer to the RU Index form below)



RU Page(TX HE-TB)



- **8** Select details
- 1. MCS rate
- 2. MU NSS: antenna number
- 3. LDPC: check for LDPC, non-check for BCC
- 4. **NSS**
- 5. Stream Idx: select 1
- 6. Length*



8* MPDU TX Length Setting in HQA

- The table shown below is implemented in QATool already.
 - → choose wanted RUs, directly shows corresponding length.
- Users are able to modify the PSDU length manually.

For NSS=1/2


PSDU Length : Short												
RU size	0	1	2	3	4	5	6	7	8	9	10	11
26	32	64	128	128	128	128	128	128	128	128	128	128
52	64	128	256	256	256	256	256	256	256	256	256	256
106	128	256	512	512	512	512	512	512	512	512	512	512
242	256	512	1024	1024	1024	1024	1024	1024	1024	1024	1024	1024
484	512	1024	2048	2048	2048	2048	2048	2048	2048	2048	2048	2048
996	1024	2048	4096	4096	4096	4096	4096	4096	4096	4096	4096	4096
006*2	2049	4006	9102	9102	9102	9102	9102	0102	9102	9102	9102	9102

For NSS=3/4


PSDU Length : long												
RU size	0	1	2	3	4	5	6	7	8	9	10	11
26	128	256	512	512	512	512	512	512	512	512	512	512
52	256	512	1024	1024	1024	1024	1024	1024	1024	1024	1024	1024
106	512	1024	2048	2048	2048	2048	2048	2048	2048	2048	2048	2048
242	1024	2048	4096	4096	4096	4096	4096	4096	4096	4096	4096	4096
484	2048	4096	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192
996	4096	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192
996*2	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192	8192



RU Page (TX HE-TB)




TX Page(TX HE-TB)




CONFIDENTIAL C

HT-TB M2W Settings

- Open Litepoint MW Web page select VSA Setting RU info.
 - 1. LTF+GI
 - 2. LDPC sym.: 1=Orange light;0=Gray light
 - PE Disamb.: 1=Orange light;
 0=Gray light
 - 4. A Factor:
 - 1. QA=0, litepont=4
 - 2. QA=1, litepont=1
 - 3. QA=2, litepont=2
 - 4. QA=3, litepont=3
 - 5. Stream: 1 or 2
 - 6. MCS rate setting: (RU-page).
 - 7. RU idx: example: 0
 - 8. Coding: LDPC or BCC




RX 11a/b/g/n/ac/ax-SU




CONFIDENTIAL C


RX 11a/b/g/n/ac/ax-SU




7 Inst RSSI WB/IB means chip-out RSSI in QATool.



RSSI Display




RX HE-MU





RX HE-MU



For example:

Wanted Station ID=888, other RUs starting from 100,101,102,....



Key-in "888" for identifying wanted Station ID



CONFIDENTIAL C

RX HE-TB

From 802.11ax:


A STA that transmits an HE TB PPDU compensates for carrier frequency offset (CFO) error and symbol clock error. After compensation, the absolute value of residual CFO error with respect to the PPDU carrying the soliciting Trigger frame shall not exceed 350 Hz for data subcarriers when measured as the 10% point of the complementary cumulative distribution function (CCDF) of CFO errors in AWGN at a received power of -60 dBm in the primary 20 MHz. The residual CFO error measurement shall be made on the HE TB PPDU following the HE-SIG-A field. The symbol clock error shall be compensated by the same ppm amount as CFO error.

- As AP in test-mode, RX HE-TB should consider frequency offset within 350Hz.
- In manual test, rough frequency offset should be calibrated in DUT first (Use TX and VSA to check and adjust Freq. offset). Then, accurate frequency adjustment should be set on VSG.




RX HE-TB

1 Use TX and VSA to check rough frequency offset




RX HE-TB







RU Page (RX HE-TB)



- 7 8 :see next page*
- Station ID
- Starting from 100, 101, 102,....





RU Page (RX HE-TB)

Allocation

8 bits indices	#1	#2	#3	#4	#5	#6	#7	#8	#9										
00000000	26	26	26	26	26	26	26	26	26	00101y ₂ y ₁ y ₀	26 26 52			2	6	106			
00000001	26	26	26	26	26	26	26	52		00110y2y1y0	52 26 26			6 2	6	106			
00000010	26	26	26	26	26	- 5	2	26 26		00111y ₂ y ₁ y ₀	52 52			2	6	106			
00000011	26	26	26	26	26	5	2	5	2	01000y2y1y0	_	1	06	2	6	26	26	26	26
00000100	26	26	5	2	26	26	26	26	26	01000y2y1y0		106				26	26		2
00000101	26	26	5	2	26	26	26	5	2				2					26	
00000110	26	26	5	2	26	5	2	26	26	01010y2y1y0	106			_	_				
00000111	26	26	5	2	26	5	2	5	2	01011y2y1y0	106			2	6	52 52		2	
00001000	5	2	26	26	26	26	26	26	26	0110y ₁ y ₀ z ₁ z ₀	106			-	-	106			
00001001	5	2	26	26	26	26	26	5	2	01110000	52 52					52 52		2	
00001010	5	2	26	26	26	5	2	26	26	01110001				42-tone					
00001011	5	2	26	26	26	5	2	5	2	01110010	,		e RU with ze correspondi						е
00001100	5	2	5	2	26	26	26	26	26	04440044					HE-SIG-B User Specific field in the				
00001101	5	2	5	2	26	26	26	5	2	01110011			correspondi	ng HE-SI	G-B Co	ntent	Channe	1	
00001110	5	2	5	2	26	5	2	26	26	10y2y1y0Z2Z1Z0		106 26 106							
00001111	5	2	5	2	26	5	2	5	2	11000y ₂ y ₁ y ₀	242								
00010y2y1y0	5	2	5	2	-	106	(numb	er of u	sers)	11001y ₂ y ₁ y ₀	484								
00011y2y1y0	106	(numb	er of u	sers)	-	5	2	5	52	11010y2y1y0				99	96				
00100y2y1y0	26	26	26	26	26		10	06		11011y2y1y0	2*996								

RU Index

MEDIATEK



CONFIDENTIAL C

RU Page (RX HE-TB)

⊢RU-Select Band: Sta ID : RU Indea MCS : PwrBoost Factor MU Nss Allocation: LDPC Nss Stream Idx Length Category: 128 1:26 *9 MCS5=5;

*MU NSS, NSS, Stream Idx

Examples	User	MU NSS (antenna number)	NSS	Stream Idx	
106+26+106 user1 user2 user3 4ss 4ss 4ss	User1~3	4	4	1	
106+26+106	User1	4	2	1* *Star	nds for 1&2
user1 user3 user4 2ss	User2	4	2	2 T	1: 1&2 2 starts from 3
user2 4ss 4ss	User3	4	4	1	
2ss	User4	4	4	1	
106+26+106	User1	4	1	1	
user1 user3 user4	User2	4	3	2	
user2 4ss 4ss	User3	4	4	1	
3ss	User4	4	4	1	45

MEDI



RX HE-TB

User number

User number limit:

• Single band:16, DBDC: 8 for each band


For example

- user #1 only: 0000 0000 0000 0001 → 0001
- user #2 only: 0000 0000 0000 0010 → 0002
- 16 users: 1111 1111 1111 → FFFF

Band Info/User Info

- "Band Info" → average PER (MAC)
- "User Info" → all users' PER separately (PHY)

BandInfo Antenna Info User Info	Common Info	
Name	Value	
PER	0.0 %	
RXOK	0	
MAC Mdrdy	Ū	
FCS en	0	
CCK PD Count	Ü	
CCK SIG Error	Ü	
OFDM PD Count	. 0	
OFDM TAQ Error	0	
CCK SFD Error	Ū.	
OFDM SIG Error	Ū.	
CCK FCS Error	ō	
OFDM FCS Error	0	
CCK MDRDY	<u> </u>	
OFDM MDRDY	0	




BandInfo Antenna Info	User Info	Common Info
Name		Value
Freq Ofset from RX 0		0
SNRO		0
FCR Error Cnt 0		0
PER 0		0.0 %
Freq Ofset from RX I		0 N
FCR Error Cnt 1		n
PER 1		0.0 %
Freq Ofset from RX 2		0
SNR 2		0
BCR From Cot 2		0
PER 2		0.0 %
Freq Ofset from RX 3		0
FCR Error Cnt 3		ñ
PER 3		0.0 %




RX HE-TB, M2W Setup

Adjust frequency more accurate by change VSG Settings' "Frequency" according to "Freq Ofset from



EEPROM






DC tone




Choose test mode



Choose type



Choose freq



Check TX tone




Adjust power level







Duplicate Mode (For EMI test)



Appendix



RU Page (HE-MU)

Allocation

8 bits indices	#1	#2	#3	#4	#5	#6	#7	#8	#9											
00000000	26	26	26	26	26	26	26	26 26		00101y ₂ y ₁ y ₀	26 26 52			2	26	106				
00000001	26	26	26	26	26	26	26	26 52		00110y2y1y0	52 26 26			26	26	106				
00000010	26	26	26	26	26	- 5	2	26 26		00111y ₂ y ₁ y ₀	52 52				26	106				
00000011	26	26	26	26	26	5	2	5	2	01000y2y1y0			06		26	26	26	26	26	
00000100	26	26	5	2	26	26	26	26 26		010003y2y1y0	106				26	26	26		2	
00000101	26	26	5	2	26	26	26	5	2					26						
00000110	26	26	5	2	26	5	2	26	26	01010y2y1y0	106					_			26	
00000111	26	26	5	2	26	5	2	52		01011y2y1y0	106				26	52 52				
00001000	5	2	26	26	26	26	26	26	26	0110y ₁ y ₀ z ₁ z ₀	106 - 106									
00001001	5	2	26	26	26	26	26	5	2	01110000	5	52 52 - 52			52					
00001010	5	2	26	26	26	5	2	26	26	01110001				242-to	one RU e	empty				
00001011	5	2	26	26	26	5	2	5	2	01110010	,		e RU with correspon						е	
00001100	5	2	5	2	26	26	26	26	26	01110011				_	HE-SIG-B User Specific field in the					
00001101	5	2	5	2	26	26	26	5	2	01110011		(correspon	ding H	E-SIG-B	Content	Channe	l		
00001110	5	2	5	2	26	5	2	26 26		10y2y1y0Z2Z1Z0		10	06		26		106			
00001111	5	2	5	2	26	5	2	5	2	11000y ₂ y ₁ y ₀	242									
00010y2y1y0	5	2	5	2	-	106 (number of users)				11001y ₂ y ₁ y ₀					484					
00011y ₂ y ₁ y ₀	106	(numb	er of u	sers)	-	5	2	5	2	11010y2y1y0					996					
00100y ₂ y ₁ y ₀	26	26	26	26	26		10	06		11011y ₂ y ₁ y ₀ 2*996										



